

# Environment Variables for Pi-hole



Variable	Default Value	Description
<code>PIHOLE_DNS_</code>	8.8.8.8;8.8.4.4	Upstream DNS servers, separated by <code>;</code> . Supports custom ports (e.g., <code>127.0.0.1#5053</code> ). DNS servers added via the web interface will be overwritten on restart.
<code>DNSSEC</code>	false	Enable DNSSEC support ( <code>true</code> or <code>false</code> ).
<code>DNS_BOGUS_PRIV</code>	true	Prevents forwarding reverse lookups for private ranges.
<code>DNS_FQDN_REQUIRED</code>	true	Prevents forwarding of non-FQDNs (Fully Qualified Domain Names).
<code>REV_SERVER</code>	false	Enables DNS conditional forwarding for local device name resolution.

Variable	Default Value	Description
<b>REV_SERVER_DOMAIN</b>	unset	Set the domain of the local network router if conditional forwarding is enabled.
<b>REV_SERVER_TARGET</b>	unset	IP of the local network router when conditional forwarding is enabled.
<b>REV_SERVER_CIDR</b>	unset	Reverse DNS zone (e.g., <code>192.168.0.0/24</code> ) for conditional forwarding.
<b>DHCP_ACTIVE</b>	false	Enable DHCP server ( <code>true</code> or <code>false</code> ).
<b>DHCP_START</b>	unset	Start IP for DHCP server (if DHCP is enabled).
<b>DHCP_END</b>	unset	End IP for DHCP server (if DHCP is enabled).
<b>DHCP_ROUTER</b>	unset	Router (gateway) IP for the DHCP server (if DHCP is enabled).
<b>DHCP_LEASETIME</b>	24	Lease time for DHCP (in hours).
<b>PIHOLE_DOMAIN</b>	lan	Domain name sent by the DHCP server.
<b>DHCP_IPv6</b>	false	Enable DHCP IPv6 support ( <code>true</code> or <code>false</code> ).
<b>DHCP_rapid_commit</b>	false	Enable DHCPv4 rapid commit.
<b>VIRTUAL_HOST</b>	<code> \${HOSTNAME}</code>	Sets the virtual host for web access (e.g., <code>http://pi.hole/admin</code> ).
<b>IPv6</b>	true	Disables IPv6 configuration when set to <code>false</code> (helpful for Unraid).
<b>TEMPERATUREUNIT</b>	c	Sets temperature unit ( <code>c</code> : Celsius, <code>k</code> : Kelvin, or <code>f</code> : Fahrenheit).
<b>WEBUIBOXEDLAYOUT</b>	boxed	Use boxed or traditional layout for the web interface.
<b>QUERY_LOGGING</b>	true	Enables or disables query logging.
<b>WEBTHEME</b>	default-light	User interface theme (options: <code>default-dark</code> , <code>default-light</code> , <code>default-auto</code> , etc.).
<b>WEBPASSWORD_FILE</b>	unset	Set admin password via Docker secrets. Ignored if <code>WEBPASSWORD</code> is set.

# Advanced Variables

Variable	Default Value	Description
<b>INTERFACE</b>	unset	NIC interface for DNS or DHCP services.
<b>DNSMASQ_LISTENING</b>	unset	Listening behavior ( <code>local</code> , <code>all</code> , <code>single</code> ).
<b>WEB_PORT</b>	unset	Custom web interface port (may affect the "blocked" page functionality).
<b>WEB_BIND_ADDR</b>	unset	Bind address for the web interface.
<b>SKIPGRAVITYONBOOT</b>	unset	Skip updating Gravity Database on boot (set to <code>1</code> to skip).
<b>CORS_HOSTS</b>	unset	List of FQDNs allowed for CORS (comma-separated).
<b>CUSTOM_CACHE_SIZE</b>	10000	Sets cache size for <code>dnsmasq</code> . Ignored if DNSSEC is enabled.
<b>FTL_CMD</b>	no-daemon	Customize <code>dnsmasq</code> options (e.g., <code>no-daemon -- --dns-forward-max 300</code> ).
<b>FTLCONF_[SETTING]</b>	unset	Customize <code>pihole-FTL.conf</code> settings (e.g., <code>FTLCONF_LOCAL_IPV4</code> ).

# Experimental Variables

Variable	Default Value	Description
<b>DNSMASQ_USER</b>	unset	Change the user that <code>FTLDNS</code> runs as ( <code>pihole</code> or <code>root</code> ).
<b>PIHOLE_UID</b>	999	Override Pi-hole's default user ID.
<b>PIHOLE_GID</b>	999	Override Pi-hole's default group ID.
<b>WEB_UID</b>	33	Override the <code>www-data</code> user ID.
<b>WEB_GID</b>	33	Override the <code>www-data</code> group ID.
<b>WEBLOGS_STDOUT</b>	0	Redirects web logs to stdout when set to <code>1</code> .

Revision #4

Created 24 September 2024 17:25:26 by aeoneros

Updated 10 October 2024 23:16:00 by aeoneros