

# GlusterFS

- [What is GlusterFS?](#)
- [Step-by-Step Guide: Setup GlusterFS](#)
- [Step-by-Step Guide: How to Mount GlusterFS on Boot](#)

# What is GlusterFS?

## GlusterFS Basic Explanation

GlusterFS is an open-source distributed file system that allows you to pool storage resources from multiple servers (nodes) into a single file system. It's designed to handle large amounts of data by distributing it across many machines, making it scalable and fault-tolerant. Essentially, GlusterFS lets you combine the storage capacity of several machines into a shared system that all machines can access.

GlusterFS is managed by the `glusterd` service, which is the core of the system. It keeps track of which files are stored on which machines and ensures that data is replicated across different nodes. This replication is useful because it allows your data to survive even if one of your nodes fails, ensuring high availability.

## Why Use GlusterFS for Syncing Docker Swarm Nodes?

When running services in Docker Swarm's replicated mode, the same service runs on multiple nodes to ensure high availability and scalability. These nodes may need to access the same set of data files, and that's where GlusterFS becomes very useful. Instead of storing separate copies of files on each node (which could lead to inconsistencies), GlusterFS ensures that all nodes share the same file system and stay in sync.

Using GlusterFS on the host system (rather than inside Docker) ensures that the file syncing works across the entire system, regardless of Docker's configuration. This setup is independent of the containers, allowing for seamless file sharing even if containers are recreated or moved to different nodes. Additionally, since GlusterFS operates at the system level, it can sync files across nodes more efficiently, avoiding network bottlenecks inside Docker containers.

Setting up GlusterFS across the nodes ensures that any file written on one node is immediately available to the others, providing data consistency and reliability when scaling services across a Docker Swarm cluster.

# Step-by-Step Guide: Setup GlusterFS

If you don't know what GlusterFS is or what it's for, you may consider checking out this [Post](#).

## Step-by-Step Guide to Setting Up GlusterFS on a 3-Node Cluster

This guide will walk you through setting up GlusterFS on a 3-node cluster using Raspberry Pis, with the IP addresses: `192.168.0.10`, `192.168.0.11`, and `192.168.0.12`. GlusterFS will be used to create a distributed, replicated file system across these nodes. Follow these steps to get your cluster up and running.

### Step 1: Install GlusterFS on All Nodes

First, you need to install the required packages on **all nodes**. The `software-properties-common` package allows managing repositories, and `glusterfs-server` installs the GlusterFS server.

```
sudo apt install software-properties-common glusterfs-server -y
```

This ensures that every node in your cluster has GlusterFS installed and ready to share and replicate files.

### Step 2: Enable Automatic Start of GlusterFS on Reboot

To ensure GlusterFS starts automatically after each reboot, you need to enable the `glusterd` service (GlusterFS daemon) on all nodes. Run this command on each node:

```
sudo systemctl start glusterd && sudo systemctl enable glusterd
```

This command starts the Gluster service immediately and ensures it starts automatically on system reboot.

### Step 3: Peer Probe the Nodes

Now, log in to the main node ( `192.168.0.10` ) via SSH as root. You need to "peer probe" the other nodes to add them to the GlusterFS cluster. The peer probe is a command that connects the other nodes to the Gluster network, allowing them to participate in the distributed file system.

On the main node ( `192.168.0.10` ), run the following commands:

```
gluster peer probe 192.168.0.11
gluster peer probe 192.168.0.12
```

The `peer probe` command tells the main node to reach out to the other nodes, establishing a connection and syncing them into the cluster.

### Step 4: Create the GlusterFS Volume

A volume in GlusterFS is essentially a storage pool made up of directories on different nodes. Here, we'll create a **replicated** volume across all three nodes. Replication ensures that the same data is stored on all nodes, making it resilient to failures.

Run the following command on the main node ( `192.168.0.10` ):

```
gluster volume create [glustername] replica 3 192.168.0.10:/root/gluster 192.168.0.11:/root/gluster
192.168.0.12:/root/gluster force
```

Explanation:

- `[glustername]` is the name you want to give to your GlusterFS volume.
- `replica 3` specifies that this is a replicated volume across all 3 nodes.
- The paths after each node's IP specify where the volume will be stored on each node ( `/root/gluster` ).

The `force` option is used to bypass potential warnings (such as creating volumes in a root directory).

### Step 5: Start the GlusterFS Volume

Once the volume is created, you need to start it. This also needs to be done on the main node:

```
gluster volume start [glustername]
```

Replace `[glustername]` with the name of the volume you created in the previous step.

## Step 6: Create a Mount Directory on Each Node

On **each node**, create a directory where you will mount the GlusterFS volume. For this guide, we'll use `/mnt/glustermount` as the mount point.

Run this command on all nodes:

```
sudo mkdir -p /mnt/glustermount
```

This ensures that the GlusterFS volume has a place to be mounted on each node.

### Step 6.1: Mount the GlusterFS Volume

Now, mount the GlusterFS volume on the `/mnt/glustermount` folder. Run this command on each node:

```
sudo mount.glusterfs localhost:[glustername] /mnt/glustermount
```

Replace `[glustername]` with the name of your volume. This mounts the volume, making it accessible from the `/mnt/glustermount` directory on each node.

To Setup Automatic Mount of GlusterFS on Boot check out this [Post](#),

Your 3-node GlusterFS cluster should now be up and running, providing a replicated and distributed file system that's resilient and ready for use!

# Step-by-Step Guide: How to Mount GlusterFS on Boot

To ensure that your GlusterFS volume is automatically mounted at boot, you'll need to make some adjustments. By default, GlusterFS volumes might not mount properly on startup due to timing issues, where the Gluster service (`glusterd`) hasn't fully started yet. The following steps provide a workaround that ensures your GlusterFS volume is mounted after boot.

This guide is based on insights from [this ServerFault discussion](#), modified to suit your 3-node Raspberry Pi setup.

## Step 1: Modify the GlusterFS Service to Wait Before Mounting

First, you need to add a script that ensures the GlusterFS service has fully started before the system attempts to mount the volume.

Run the following command to edit the `glusterd.service`:

```
sudo systemctl edit glusterd.service
```

This will open a text editor. Add the following configuration to ensure a delay in mounting the GlusterFS volume:

```
[Service]
ExecStartPost=/usr/local/sbin/glusterfs-wait
```

Save and exit the editor.

## Step 2: Create the `glusterfs-wait` Script

Next, create a script that checks if the GlusterFS volume is ready to be mounted. This script will be called after the Gluster service starts and will retry the mount command until it succeeds.

Create the script file:

```
sudo nano /usr/local/sbin/glusterfs-wait
```

Paste the following content into the file:

```
#!/bin/bash
FAIL=1
until [ $FAIL -eq 0 ]; do
    gluster volume status all
    FAIL=$?
    test $FAIL -ne 0 && sleep 1
done
exit 0
```

Save and close the file.

This script will keep checking the status of the GlusterFS volume every second until the volume is ready.

## Step 3: Make the Script Executable

You need to make the script executable so it can run at startup.

Run this command:

```
sudo chmod +x /usr/local/sbin/glusterfs-wait
```

## Step 4: Create a Mount Override

To ensure that the GlusterFS mount happens after the `glusterd.service` is up and running, you need to create a mount override.

For the example folder `/mnt/glustermount`, run the following command:

```
sudo systemctl edit mnt-glustermount.mount
```

In the text editor, paste the following content:

```
[Unit]
```

```
After=glusterd.service
```

```
Wants=glusterd.service
```

This ensures that the mount service will wait for the `glusterd` service to start.  
Save and close the editor.

## Step 5: Reload the Systemd Daemon and Reboot

To apply the changes, reload the systemd daemon with the following command:

```
sudo systemctl daemon-reload
```

Then, reboot your system:

```
sudo reboot
```

## Step 6: Verify GlusterFS Mount After Reboot

After the system reboots, check the status of the GlusterFS service and ensure the volume is mounted correctly:

```
systemctl status glusterd.service
```

You should see that the GlusterFS volume has mounted successfully, and the service is running without issues.

This setup ensures that your GlusterFS volumes are reliably mounted after each system boot.